



IAM

Health Check

11.x Above



Catatan Perubahan

Tanggal	Deskripsi Perubahan
September 9, 2020	Rilis Dokumen di atas11.x.

Daftar Isi

1	Skenario Aplikasi.....	1
2	Konfigurasi dan Tangkapan Layar	1
2.1	Unduh Health Check Tool dari Sangfor Community	1
2.2	Login IAM Menggunakan Sangfor Firmware Updater	2
3	Hasil.....	3
4	Tindakan Pencegahan.....	4

1 Skenario Aplikasi

Client atau Pengguna ingin melakukan health check di IAM.

2 Konfigurasi dan Tangkapan Layar

2.1 Unduh Health Check Tool dari Sangfor Community

Mengunjungi <https://community.sangfor.com/>

Path: Self Service > Download > Tools

Health Check Tool for IAM

Support the version later than 11.X

Last Update: 27 Jul 2017 16:32 Size: 63KB File MD5: F7FEE34C2221314C309B771CBF1569AE

Download

Unduh juga Sangfor Firmware Updater

Sangfor Firmware Updater


Tool used to install update package on any Sangfor product(excluding Sangfor HCI)

Last Update: 12 Jun 2019 11:12 Size: 3.08 MB File MD5: 19E64BF5121E2D4E7C49FF9908818513

Download


2.2 Login IAM Menggunakan Sangfor Firmware Updater

STARTUP	9/9/2020 3:37 AM	File folder	
SANGFOR Firmware Updater.exe	3/31/2012 5:55 PM	Application	531 KB




Setelah login, tekan F10. Tangkapan layar di bawah ini akan ditampilkan.

Pilih Command > Check Device Health



Klik Browse dan pilih Health Check yang baru saja diunduh.

Anda dapat menentukan hasil simpan path . Setelah itu klik Start.



3 Hasil

The health report akan dibuat di bawah path yang Anda pilih sebelumnya.

STARTUP	9/9/2020 6:43 AM	File folder	
HealthReport.html	9/9/2020 6:43 AM	HTML File	14 KB
SANGFOR Firmware Updater.exe	3/31/2012 5:55 PM	Application	531 KB

4 Tindakan Pencegahan

1. Health Report dalam txt format secara default, Anda perlu mengubahnya ke format html untuk membacanya.

Before

 HealthReport.txt	9/9/2020 6:43 AM	Text Document	14 KB
--	------------------	---------------	-------

After

 HealthReport.html	9/9/2020 6:43 AM	HTML File	14 KB
---	------------------	-----------	-------

2. Script hanya mendukung perangkat dengan 11.x dan di atas.



Copyright © SANGFOR Technologies Inc. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of SANGFOR Technologies Inc.

SANGFOR is the trademark of SANGFOR Technologies Inc. All other trademarks and trade names mentioned in this document are the property of their respective holders.

Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied. The information in this document is subject to change without notice. To obtain the latest version, contact the international service center of SANGFOR Technologies Inc